**Threads and Concurrency key concepts:** threads, concurrent execution, timesharing, context switch, interrupts, preemption

Lesley Istead

David R. Cheriton School of Computer Science University of Waterloo

Spring 2021

### ... a sequence of instructions.

- A normal sequential program consists of a single thread of execution.
- Threads provide a way for programmers to express concurrency in a program.
- In threaded concurrent programs there are multiple threads of execution, all occuring at the same time.
  - Threads may perform the same task.
  - Threads may perform different tasks.

#### Recall: Concurrency

... multiple programs or sequences of instructions running, or appearing to run, at the same time.

# Why Threads?

- **Resource Utilization:** blocked/waiting threads give up resources, i.e., the CPU, to others.
- Parallelism: multiple threads executing simultaneously; improves performance.
- Responsiveness: dedicate threads to UI, others to loading/long tasks.
- Priority: higher priority; more CPU time, lower priority; less CPU time.
- **5** Modularization: organization of execution tasks/responsibilities.

#### Blocking

Threads may **block**, ceasing execution for a period of time, or, until some condition has been met. When a thread blocks, it is not executing instructions—the CPU is idle. Concurrency lets the CPU execute a different thread during this time. **CPU time is money!** 

# OS/161 Threaded Concurrency Examples

Key ideas from the examples:

- A thread can create new threads using thread\_fork
- New theads start execution in a function specified as a parameter to thread\_fork
- The original thread (which called thread\_fork) and the new thread (which is created by the call to thread\_fork) proceed concurrently, as two simultaneous sequential threads of execution.
- All threads share access to the program's global variables and heap.
- Each thread's stack frames are private to that thread; each thread has its own stack.

#### In the OS

... a thread is represented as a structure or object.

# OS/161's Thread Interface

#### ■ create a new thread:

```
int thread_fork(
  const char *name, // name of new thread
  struct proc *proc, // thread's process
  void (*func) // new thread's function
  (void *, unsigned long),
  void *data1, // function's first param
  unsigned long data2 // function's second param
);
```

terminate the calling thread:

```
void thread_exit(void);
```

volutarily yield execution:

```
void thread_yield(void);
```

See kern/include/thread.h


# Other Thread Libraries and Functions

- join a common thread function to force one thread to block until another finishes; NOT offered by OS/161
- pthreads POSIX threads, a well-supported, popular, and sophisticated thread API
- OpenMP a cross-platform, simple multi-processing and thread API
- GPGPU Programming general-purpose GPU programming APIs, e.g. nVidia's CUDA, create/run threads on GPU instead of CPU

#### Concurrency and Threads

- originated in 1950s to improve CPU utilization during I/O operations
- "modern" timesharing originated in the 1960s

# Review: Sequential Program Execution



### The Fetch/Execute Cycle

- **1 fetch** instruction PC points to
- 2 decode and execute instruction
- 3 increment the PC


num	name	use	num	name	use
0	z0	always zero	24-25	t8-t9	temps (caller-save)
1	at	assembler reserved	26-27	k0-k1	kernel temps
2	v0	return val/syscall $\#$	28	gp	global pointer
3	v1	return value	29	sp	stack pointer
4-7	a0-a3	subroutine args	30	s8/fp	frame ptr (callee-save)
8-15	t0-t7	temps (caller-save)	31	ra	return addr (for jal)
16-23	s0-s7	saved (callee-save)			

conventions enforced in compiler; used in OS

- caller-save: it is the responsibility of the calling function to save/restore values in these registers
- callee-save: it the the responsibility of the called function to save/restore values in these registers before/after use

callee/caller save strategy attempts to minimize the callee saving values the caller does not use


# Review: The Stack



# FuncA() { . . . FuncB(); . . . FuncB() { . . . FuncC(); . . . Recall: Functions push argu-

Functions push arguments (a0-a3), return address, local variables, and temporaryuse registers onto the stack.

# Concurrent Program Execution (Two Threads)



Conceptually, each thread executes sequentially using its private register contents and stack.

What options exist?

- **Hardware support.** *P* processors, *C* cores, *M* multithreading per core  $\Rightarrow$  *PCM* threads can execute **simultaneously**.
- Timesharing. Multiple threads take turns on the same hardware; rapidly switching between threads so all make progress.
- **Hardware support + Timesharing.** *PCM* threads running simultaneously with timesharing.

#### Example: Intel i9-9900X

... 10 cores, each core can run 2 threads (multithreading degree). Therefore, P = 1, C = 10, and M = 2, so PCM = 20 threads can run simultaneously. Note that while cores of a single processor share caches (L2, L3), threads execute separately.

# Timesharing and Context Switches

- When timesharing, the switch from one thread to another is called a context switch
- What happens during a context switch:
  - 1 decide which thread will run next (scheduling)
  - 2 save register contents of current thread
  - 3 load register contents of next thread
- Thread context must be saved/restored carefully, since thread execution continuously changes the context

#### Timesharing

... each thread gets a small amount of time to execute on the CPU, when it expires, a context switch occurs. Threads share the CPU, giving the user the illusion of multiple programs running at the same time.

```
/* See kern/arch/mips/thread/switch.S */
switchframe switch:
 /* a0: address of switchframe pointer of old thread. */
 /* a1: address of switchframe pointer of new thread. */
  /* Allocate stack space for saving 10 registers. 10*4 = 40 */
  addi sp, sp, -40
       ra, 36(sp) /* Save the registers */
   SW
       gp, 32(sp)
  SW
      s8, 28(sp)
  SW
      s6, 24(sp)
  SW
      s5, 20(sp)
  SW
      s4, 16(sp)
  SW
      s3, 12(sp)
  SW
  sw s2, 8(sp)
      s1, 4(sp)
  SW
       s0, 0(sp)
  SW
   /* Store the old stack pointer in the old thread */
       sp, 0(a0)
   SW
```

```
/* Get the new stack pointer from the new thread */
    sp, 0(a1)
lw
nop
             /* delay slot for load */
/* Now, restore the registers */
lw
    s0, 0(sp)
lw s1, 4(sp)
lw s2, 8(sp)
lw s3, 12(sp)
lw s4, 16(sp)
lw s5, 20(sp)
lw s6, 24(sp)
lw s8, 28(sp)
lw gp, 32(sp)
   ra, 36(sp)
lw
                    /* delay slot for load */
nop
/* and return. */
j ra
addi sp, sp, 40 /* in delay slot */
.end switchframe switch
```

# Switchframe Notes

- switchframe\_switch is called by C function thread\_switch
  - thread\_switch is the caller; it will save/restore the caller-save registers
  - switchframe\_switch is the callee; it must save/restore the callee-save registers
  - switchframe\_switch, saves callee-save registers to the old thread stack; it restores the callee-save registers from the new threads stack
- MIPS R3000 is pipelined; delay-slots are used to protect against:
  - load-use hazards, where loaded values are used in the next instruction
  - control hazards, where we don't know which instruction to fetch next


# What Causes Context Switches?

- the running thread calls thread\_yield
  - running thread voluntarily allows other threads to run
- the running thread calls thread\_exit
  - running thread is terminated
- the running thread **blocks**, via a call to **wchan\_sleep** 
  - more on this later . . .
- the running thread is preempted
  - running thread involuntarily stops running


#### The OS

... strives to maintain high CPU utilization. Hence, in addition to timesharing, context switches occur whenever a thread ceases to execute instructions.

## Thread States




running: currently executingready: ready to executeblocked: waiting for something, so not ready to execute.



- timesharing—concurrency achieved by rapidly switching between threads
  - how rapidly? impose a limit on CPU time, the scheduling quantum
  - the quantum is an upper bound on how long a thread can run before it must yield the CPU
- how do you stop a running thread, that never yields, blocks or exits when the quantum expires?
  - preemption forces a running thread to stop running, so that another thread can have a chance
  - to implement preemption, the thread library must have a means of "getting control" (causing thread library code to be executed) even though the running thread has not called a thread library function
  - this is normally accomplished using interrupts

- an interrupt is an event that occurs during the execution of a program
- interrupts are caused by system devices (hardware), e.g., a timer, a disk controller, a network interface
- when an interrupt occurs, the hardware automatically transfers control to a fixed location in memory
- at that memory location, the thread library places a procedure called an interrupt handler
- the interrupt handler normally:
  - create a trap frame to record thread context at the time of the interrupt
  - 2 determines which device caused the interrupt and performs device-specific processing
  - **3** restores the saved thread context from the trap frame and resumes execution of the thread


# OS/161 Thread Stack after in Interrupt




- A preemptive scheduler uses the scheduling quantum to impose a time limit on running threads
- Threads may block or yield before their quantum has expired.
- Periodic timer interrupts allow running time to be tracked.
- If a thread has run too long, the timer interrupt handler preempts the thread by calling thread\_yield.
- The preempted thread changes state from running to ready, and it is placed on the ready queue.
- Each time a thread goes from ready to running, the runtime starts out at 0. Runtime does not accumulate.


OS/161 threads use preemptive round-robin scheduling.

### OS/161 Thread Stack after Preemption







Thread 1 is **RUNNING**. Thread 2 is **READY**, having called thread\_yield previously.




A timer interrupt occurs.




Thread 1 is preempted, a trapframe is created to save its context.




The timer interrupt handler determines what happened, and, calls the appropriate handler.




Thread 1 has exceeded its quantum. Yield the CPU to another thread, call thread\_yield.




 $\mathsf{High}\mathsf{-}\mathsf{level}$  context switch: choose new thread, save caller-save registers.




Low-level context switch. Save callee-save registers.




Thread 2 is now **RUNNING**, Thread 1 is now **READY**. Thread 2 returns from low-level context switch, restoring callee-save registers.




Return from high-level context switch, restoring caller-save registers.




Return from yield. Context is fully restored. Thread 2 is now running its regular program.




Thread 2 yields.




High-level context switch.




Low-level context switch.




Thread 1 is now **RUNNING**. Thread 2 is now **READY**. Return from low-level context switch.




Return from high-level context switch.



Return from yield.



Return from interrupt handling functions.



Restore thread 1's context (stored in the trap frame), return to regular program.